

Viz Arc Release Notes

Version 1.7





Copyright ©2022Vizrt. All rights reserved.

No part of this software, documentation or publication may be reproduced, transcribed, stored in a retrieval system, translated into any language, computer language, or transmitted in any form or by any means, electronically, mechanically, magnetically, optically, chemically, photocopied, manually, or otherwise, without prior written permission from Vizrt.

Vizrt specifically retains title to all Vizrt software. This software is supplied under a license agreement and may only be installed, used or copied in accordance to that agreement.

Disclaimer

Vizrt provides this publication "as is" without warranty of any kind, either expressed or implied. his publication may contain technical inaccuracies or typographical errors. While every precaution has been taken in the preparation of this document to ensure that it contains accurate and up-to-date information, the publisher and author assume no responsibility for errors or omissions. Nor is any liability assumed for damages resulting from the use of the information contained in this document. Vizrt's policy is one of continual development, so the content of this document is periodically subject to be modified without notice. These changes will be incorporated in new editions of the publication. Vizrt may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time. Vizrt may have patents or pending patent applications covering subject matters in this document. The furnishing of this document does not give you any license to these patents.

Antivirus

Vizrt does not recommend or test antivirus systems in combination with Vizrt products, as the use of such systems can potentially lead to performance losses. The decision for the use of antivirus software and thus the risk of impairments of the system is solely at the customer's own risk.

There are general best-practice solutions, these include setting the antivirus software to not scan the systems during operating hours and that the Vizrt components, as well as drives on which clips and data are stored, are excluded from their scans (as previously stated, these measures cannot be guaranteed).

Technical Support

For technical support and the latest news of upgrades, documentation, and related products, visit the Vizrt web site at www.vizrt.com.

Created on

2022/11/15

Contents

1	Viz Arc 1.7.0	5
1.1	New Features	5
1.1.1	New Object Tracker 1.1	
1.1.2	LoupeDeck Integration	
1.1.3	Improved Unreal Integration	5
1.1.4	Improved Licensing Options	5
1.1.5	Graphic Hub Refactoring	5
1.1.6	Improved JSON Data Integration	6
1.2	Important Changes	6
1.3	Known Issues	6
1.4	Fixed Issues	
1.5	Compatibility Notes	
2	Documentation	
3	Support	

- Viz Arc 1.7.0
 - New Features
 - · Important Changes
 - Known Issues
 - Fixed Issues
 - · Compatibility Notes
- Documentation
- Support

1 Viz Arc 1.7.0

Release Date: 2022-11-15

These are the release notes for Viz Arc version 1.7.0. This document describes the user-visible changes that have been made to the software since Viz Arc 1.6.0.

1.1 New Features

1.1.1 New Object Tracker 1.1

- · Improved tracking quality.
- · Improved performance (in Viz Arc as well).
- · Automatic handling of delays, making it easier to set-up and operate.
- · Easy mouse interaction allowing to position graphics in relation to the tracking point.

1.1.2 LoupeDeck Integration

- Integration of the LoupeDeck Live device that gives the user a nice way to control the Precision Keyer through a hardware device.
- · Precision Keyer UI has been revisited and improved.

1.1.3 Improved Unreal Integration

- · Ability to control UE content through the new ControlObject integration in Viz Engine 5.
- · Control the Level Blueprint through Viz Arc.
- Unreal Commands (ability to send specific commands to the Unreal Engine, just like Viz Engine commands).

1.1.4 Improved Licensing Options

- · Ability to select license type CORE or FREEMIUM.
- Ability to select preferred license source (for example, network, local or both) and to establish an order of priority (for example, network first, local first).

1.1.5 Graphic Hub Refactoring


We refactored the Graphic Hub browser which is now based on web technologies (Vue). The performance and usability has been dramatically improved. In this release, we use this browser only for the Scene Browser (and replace all other browser instances in future releases).

1.1.6 Improved JSON Data Integration

Some scripting UI elements such as TextBoxes, Lists and DropDowns can be easily populated using **JSONPath** queries.

1.2 Important Changes

- · Bundle Installer now includes the CodeMeter runtime installer.
- New Graphic Hub browser (for scene browsing only) is enabled by default and can be switched off returning to the old Graphic Hub browser. A regular expression can be used to ignore certain Actor names when parsing for Unreal BluePrint's. The default value is bCanBeDamaged.



1.3 Known Issues

- SHM output does not work when using a Viz Engine version <= 4.2 in non-Matrox Mode using the Viz Engine Render Pipeline.
- SHM output is flipped vertically in Viz Engine versions 4.x when using Viz Engine Render Pipeline.

1.4 Fixed Issues

- · Executing play on a sequence animation action crashes Unreal Engine 5.0 (ARC-235).
- When using animation interpolation in Unreal, sometimes the animation could incorrectly reference a previously selected keyframe (ARC-222).
- When using blueprint trigger functions, the functions won't execute when playing the template in the template editor (ARC-205).
- The refresh button in the Unreal Blueprint action does not work (ARC-196).
- · An Unreal template loses the associated update/execute function when refreshed (ARC-78).
- · Dropdowns in Viz Container scripts are not supported by the Script Action (ARC-207).
- · Scripting Tab UI elements do not trigger the OnParameterChanged callback (ARC-216).
- · Can't enter } in script code editor using a German keyboard layout (ARC-211).
- Scene based actions reference the wrong scene when multiple scenes were opened and selected on the Scenes Tabs (ARC-212).
- · Searching actions within groups is not working (ARC-215).
- Image Assets scripting UI elements don't accept sources (for example, scenes) other than images (ARC-227).
- Scene based actions do not reference the default <program>, but the channel that is selected on the Scene Tab when the action is created (ARC-237).
- Using the delete key in a playlist element time editor removes the playlist element (ARC-238).

1.5 Compatibility Notes

Viz Arc 1.7.0 is compatible with:

Product	Version
Viz Engine	3.12 and newer, Viz Engine 4.x.
Viz Virtual Studio	1.1.0 and newer.
Unreal Engine	4.26.x, 4.27.x, 5.0.x.
Graphic Hub REST	2.5.0 and newer.
Media Sequencer	5.1.3 and newer.
Coder	2.3.1 and newer.
Viz Pilot Data Server	8.1.0 and newer.

Product	Version
Media Service	2.3.3 and newer.
Viz One	7.1.0 and newer.
Viz Object Tracker	1.1
Viz Arena	5.1.0

2 Documentation

Documentation for Viz Arc is available at the Vizrt Documentation Center:

- · Viz Arc User Guide
- · Viz Arc Script Guide

3 Support

Support is available at the Vizrt Support Portal.